

S I S I * AMS2 REPORTS MANUAL * RELEASE 10.0

BLANK STOCK POSITION/NEEDS REPORT

:-----:
: 575 :
:-----:

DESCRIPTION: REPORT SHOWS POSITION, NEEDS, WORK IN PROCESS, AND INVENTORY BY TIME PERIOD, FOR ALL SELECTED LEVELS OF MANUFACTURING FROM BLANK STOCK. RUN MPC576 FOR SAME INFORMATION WITH SIZE BREAKDOWNS. SET UP PARM575 BEFORE RUNNING EITHER REPORT.

SWITCHES: NO SWITCHES AVAILABLE

OPTIONS: 1346 NOT REQUIRED. USE TABLE 7 OF AMSAUX INSTEAD OF TABLE 70 FOR LONG DESCRIPTION.

1349 NOT REQUIRED. USES TABLE FC (NOTE: IF THIS OPTION IS ON, AND TABLE 'FC' IS NOT BUILT, PROGRAM WILL AUTOMATICALLY ADD 7 DAYS TO WIP COMP DATES WHEN PRINTING ON REPORT).

IF 'REVISED COMPLETION' DATE IS USED, THE CALCULATION IS BASED ON IT INSTEAD OF ON 'COMPLETION' DATE.

TABLES: 'LV' IN AMS2 (LEVEL DESCRIPTION). DEFAULT IF NO TABLES TO 'LEVEL1', 'LEVEL2', 'LEVEL3'.

'FC' (NOT REQUIRED). PERMITS ENTRY FOR # OF DAYS TO BE ADDED TO WIP COMPL-DATE AS SHOWN ON REPORT.

EX: FC LITERAL 5 DAYS

RUN INSTRUCTIONS: RUN ON-LINE HOUSE. RUN MPC575.PUB.AMS2

ENTER REPORT PARAMETER CARD NUMBER **XXX** (RET) (SET UP IN PARM 575)

ENTER STARTING DATE (RETURN FOR CURRENT DATE)

STYLES SELECT (SUBORDINATE LEVELS WILL AUTOMATICALLY BE SELECTED)

ENTER STYLE OR STYLE/CLR (RETURN FOR ALL) (UP TO 1000 SELECTS).

HIT 'RETURN' WHEN YOU HAVE NO MORE SELECTS.

REPORT WILL NOW RUN.

YOUR SCREEN WILL DISPLAY THE COMPUTATION STEP AS THE DATA ACCUMULATES. THESE DISPLAYS ARE PROVIDED TO INFORM YOU AS TO THE STATUS OF YOUR PROGRAM. YOUR FINAL DISPLAY WILL BE 'END OF PROGRAM'.

DISPLAYS ARE:

1000	GATHER RECORDS	3100	CALCULATE NEEDS
1100	GET STYLES	4000	SORT
1200	GET WIP	5000	REPORT
1300	GET LINES	9900	CLOSING ROUTINE
2000	ATTACH RELATIVES		
3000	SORT CALC NEEDS		:END OF PROGRAM