

S I S I * AMS2 REPORTS MANUAL * RELEASE 10.0

680

ACCOUNTANTS MATERIAL INVENTORY

DESCRIPTION: USEFUL TO COMPARE THE COMPUTERS WORK-IN-PROCESS
----- WITH THAT OBSERVED FROM A PHYSICAL INVENTORY, WITH COLUMNS AVAILABLE
FOR MANUAL FIGURES TO BE WRITTEN.
SELECTIONS TO INCLUDE/EXCLUDE FABRIC GROUPS UP TO 10 ARE
AVAILABLE. LOCATION RECAP WILL PRINT AT END OF REPORT SHOWING
YARDS AND DOLLARS PER LOCATION WHEN USER ANSWERS Y TO PRINT
FABRIC LOCATION DETAILS.

SWITCHES:

NO SWITCHES FOR THIS REPORT

OPTIONS:

0586 680 BREAK & TOTAL ON FAB. THE PROGRAM WILL BREAK ON A CHANGE OF FABRIC
AND GIVE THE TOTAL INVENTORY-QTY & EXTENDED-COST FOR THAT FABRIC.

849 REPLACES "LOC" WITH "DYE LOT"

1435 USE TRANSFER FIELDS

1496 GET BOOK COST FROM FAB DATABASE

RUN INSTRUCTIONS:

:RUN MCP.PUB.AMS2
ENTER HOUSE:
R R680
ENTER INPRI: _#
ENTER PRINT OUTPRI: _#
PRINT FABRIC WITH ZERO INVENTORY (Y/N)?: _#
PRINT FABRIC LOCATION DETAILS (N/Y):#
ENTER TYPE, 1 - FABRIC, 2 - TRIM, RETURN FOR ALL:#
ENTER STANDARD COST (Y/N):__
ENTER INV BASE
1=STD, 2=ACTUAL, 3=STD LESS B, 4=ACTUAL LESS B: _#
ENTER 'I' TO INCLUDE OR 'E' TO EXCLUDE FABRIC GROUPS:
ENTER UP TO 10 FABRIC GROUPS, 2 CHARACTER EACH
SORT BY FABRIC GROUP (Y/N):
ENTER SWR#:

REPORT